

Mme STITOU

03/12/2024

Compte rendu

Compte rendu Stormshield +
contexte réseau

TEWES Arnaud

BTS SIO SISR 2EME ANNEE

1. Configuration SNS interne

The screenshot shows the Stormshield Network Security v4.0.1 interface. The left sidebar contains a tree view with 'CONFIGURATION' selected, and 'NETWORK' expanded. The main panel is titled 'NETWORK / INTERFACES' and displays a table of network interfaces. The table has columns for Interface, Port, Type, Status, IPv4 address, and Comments. The 'in' interface is highlighted in yellow. Below the table are 'CANCEL' and 'APPLY' buttons.

Interface	Port	Type	Status	IPv4 address	Comments
out	1	Ethernet, 1 Gb/s		172.16.69.254/24	
in	2	Ethernet, 1 Gb/s		192.168.67.1/24	
SERVEUR	3	Ethernet, 1 Gb/s		192.168.69.1/28	
BACKUP	4	Ethernet, 1 Gb/s		192.168.69.17/29	
LOG	5	Ethernet, 1 Gb/s		192.168.69.25/29	
MNG	6	Ethernet, 1 Gb/s		192.168.69.33/29	
User1_110	7	Ethernet, 1 Gb/s		192.168.69.65/26	
User2_120	8	Ethernet, 1 Gb/s		192.168.69.129/26	

General

Default gateway (router):

The screenshot shows the Stormshield Network Security v4.0.1 interface. The left sidebar contains a tree view with 'CONFIGURATION' selected, and 'NETWORK' expanded. The main panel is titled 'NETWORK / DHCP' and displays the 'General' tab. The 'ON' toggle is checked. The 'DHCP server' radio button is selected. The 'Default settings' section shows 'DHCP server(s)' as 'SRV-VAD1-AT' and 'IP address used to relay DHCP queries' as 'Firewall_in'. The 'Relay DHCP queries for all interfaces' checkbox is unchecked. The 'LISTENING INTERFACES ON THE DHCP RELAY SERVICE' section has an 'Add' button and a table with one row for 'Interface'. Below the table are 'CANCEL' and 'APPLY' buttons.

General

☒ ON

☐ DHCP server
☒ DHCP relay

Default settings

DHCP server(s):

IP address used to relay DHCP queries:

☐ Relay DHCP queries for all interfaces.

LISTENING INTERFACES ON THE DHCP RELAY SERVICE

+ Add -X Delete

Interface


The screenshot shows the Stormshield Network Security v4.0.1 interface. The left sidebar contains a tree view with 'CONFIGURATION' selected, and 'SECURITY POLICY' expanded. The main panel is titled 'SECURITY POLICY / FILTER - NAT' and displays a table of NAT rules. The table has columns for Status, Action, Source, Destination, Dest. port, Protocol, Security inspection, and Comments. The first rule is highlighted in yellow. Below the table are 'CANCEL' and 'APPLY' buttons.

SECURITY POLICY / FILTER - NAT



(1) Block all




FILTERING NAT

Status	Action	Source	Destination	Dest. port	Protocol	Security inspection	Comments
ON	pass	Any	Any	Any			Created on 2024-08-28 13:31:48, by adm...







2. Configuration SNS externe








3. Cartes réseau Stormshield









2 SIO - CLI-V-01-AT	Exécution	0 %	4096 Mo
2 SIO - CLI-V-MNG-AT	Désactivé		
2 SIO - HA-Proxy1	Désactivé		
2 SIO - HA-Proxy2	Désactivé		
2 SIO - HA-Proxy3	Désactivé		
2 SIO - HA-Proxy4	Désactivé		
2 SIO - HA-Proxy5	Désactivé		
2 SIO - KaliLinux	Désactivé		
2 SIO - SNS-AT	Exécution	0 %	2048 Mo
2 SIO - SNSEXT-AT	Exécution	0 %	2048 Mo
2 SIO - SRV-SQL1-AT	Désactivé		
2 SIO - SRV-SQL2-AT	Désactivé		
2 SIO - SRV-V-AD1-AT	Exécution	0 %	4096 Mo
2 SIO - SRV-V-AD2-AT	Exécution	0 %	4096 Mo
2 SIO - SRV-V-BKP-AT	Exécution	0 %	16384 Mo
2 SIO - SRV-V-FS2-AT	Désactivé		
2 SIO - SRV-V-FS-AT	Désactivé		
2 SIO - SRV-V-GLPI-AT	Désactivé		
2 SIO - SRV-V-LOG-AT	Désactivé		
2 SIO - SRV-V-MNG-AT	Désactivé		
2 SIO - SRV-V-RDS-AT	Désactivé		
2 SIO - SRV-V-WDS-AT	Désactivé		
2 SIO - WordPress - AT	Désactivé		